

NAG Library Routine Document

D03RZF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

D03RZF is designed to be used in conjunction with D03RBF. It can be called from the MONITR to obtain the number of grid points and their (x, y) co-ordinates on a solution grid.

2 Specification

```
SUBROUTINE D03RZF(LEVEL, NLEV, XMIN, YMIN, DXB, DYB, LGRID, ISTRUC,
1              NPTS, X, Y, LENXY, IFAIL)
      INTEGER          LEVEL, NLEV, LGRID(*), ISTRUC(*), NPTS, LENXY, IFAIL
      double precision  XMIN, YMIN, DXB, DYB, X(LenXY), Y(LenXY)
```

3 Description

D03RZF extracts the number of grid points and their (x, y) co-ordinates on a specific solution grid produced by D03RBF. It must be called only from within the MONITR. The parameters NLEV, XMIN, YMIN, DXB, DYB, LGRID and ISTRUC to MONITR must be passed unchanged to D03RZF.

4 References

None.

5 Parameters

- | | | |
|----|---|--------------|
| 1: | LEVEL – INTEGER | <i>Input</i> |
| | <i>On entry:</i> the grid level at which the co-ordinates are required. | |
| | <i>Constraint:</i> $1 \leq \text{LEVEL} \leq \text{NLEV}$. | |
| 2: | NLEV – INTEGER | <i>Input</i> |
| 3: | XMIN – double precision | <i>Input</i> |
| 4: | YMIN – double precision | <i>Input</i> |
| 5: | DXB – double precision | <i>Input</i> |
| 6: | DYB – double precision | <i>Input</i> |
| 7: | LGRID(*) – INTEGER array | <i>Input</i> |
| 8: | ISTRUC(*) – INTEGER array | <i>Input</i> |

Note: the dimension of the array LGRID must be at least NLEV.

The dimension of the array ISTRUC must be at least $\text{LGRID}(\text{NLEV}) + 2 \times \text{nrows} + \text{NPTS} + 1$ where *nrows* is stored in $\text{ISTRUC}(\text{LGRID}(\text{NLEV}))$ and is the number of rows in the grid at level NLEV

On entry: NLEV, XMIN, YMIN, DXB, DYB, LGRID and ISTRUC as supplied to MONITR must be passed unchanged to D03RZF.

- | | | |
|----|--|---------------|
| 9: | NPTS – INTEGER | <i>Output</i> |
| | <i>On exit:</i> the number of grid points in the grid level LEVEL. | |

- 10: X(LENXY) – *double precision* array *Output*
 11: Y(LENXY) – *double precision* array *Output*
- On exit:* X(*i*) and Y(*i*) contain the (*x*, *y*) co-ordinates respectively of the *i*th grid point, for *i* = 1, 2, ..., NPTS.
- 12: LENXY – INTEGER *Input*
- On entry:* the dimension of the arrays X and Y as declared in the (sub)program from which D03RZF is called.
- Constraint:* LENXY ≥ NPTS.
- 13: IFAIL – INTEGER *Input/Output*
- On entry:* IFAIL must be set to 0, −1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.
- On exit:* IFAIL = 0 unless the routine detects an error (see Section 6).
- For environments where it might be inappropriate to halt program execution when an error is detected, the value −1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. **When the value −1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or −1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, LEVEL < 1,
or LEVEL > NLEV.

IFAIL = 2

The dimension of the arrays X and Y is too small for the requested grid level, i.e., LENXY < NPTS.

7 Accuracy

Not applicable.

8 Further Comments

None.

9 Example

See Section 9 in D03RBF.