

NAG Library Routine Document

F01CRF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

F01CRF transposes a rectangular matrix in-situ.

2 Specification

```
SUBROUTINE F01CRF(A, M, N, MN, MOVE, LMOVE, IFAIL)
INTEGER          M, N, MN, MOVE(LMOVE), LMOVE, IFAIL
double precision A(MN)
```

3 Description

F01CRF requires that the elements of an m by n matrix A are stored consecutively by columns in a one-dimensional array. It reorders the elements so that on exit the array holds the transpose of A stored in the same way. For example, if $m = 4$ and $n = 3$, on entry the array must hold:

$$a_{11} \quad a_{21} \quad a_{31} \quad a_{41} \quad a_{12} \quad a_{22} \quad a_{32} \quad a_{42} \quad a_{13} \quad a_{23} \quad a_{33} \quad a_{43}$$

and on exit it holds

$$a_{11} \quad a_{12} \quad a_{13} \quad a_{21} \quad a_{22} \quad a_{23} \quad a_{31} \quad a_{32} \quad a_{33} \quad a_{41} \quad a_{42} \quad a_{43}.$$

4 References

Cate E G and Twigg D W (1977) Algorithm 513: Analysis of in-situ transposition *ACM Trans. Math. Software* **3** 104–110

5 Parameters

- | | | |
|----|---|---------------------|
| 1: | A(MN) – double precision array | <i>Input/Output</i> |
| | <i>On entry:</i> the elements of the m by n matrix A , stored by columns. | |
| | <i>On exit:</i> the elements of the transpose matrix, also stored by columns. | |
| 2: | M – INTEGER | <i>Input</i> |
| | <i>On entry:</i> m , the number of rows of the matrix A . | |
| 3: | N – INTEGER | <i>Input</i> |
| | <i>On entry:</i> n , the number of columns of the matrix A . | |
| 4: | MN – INTEGER | <i>Input</i> |
| | <i>On entry:</i> n , the value $m \times n$. | |
| 5: | MOVE(LMOVE) – INTEGER array | <i>Workspace</i> |
| 6: | LMOVE – INTEGER | <i>Input</i> |
| | <i>On entry:</i> the dimension of the array MOVE as declared in the (sub)program from which F01CRF is called. | |

Suggested value: $LMOVE = (m + n)/2$.

Constraint: $LMOVE \geq 1$.

7: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, $MN \neq M \times N$.

IFAIL = 2

On entry, $LMOVE \leq 0$.

IFAIL < 0

A serious error has occurred. Check all subroutine calls and array sizes. Seek expert help.

7 Accuracy

Exact results are produced.

8 Further Comments

The time taken by F01CRF is approximately proportional to mn .

9 Example

This example transposes a 7 by 3 matrix and prints out, for convenience, its transpose.

9.1 Program Text

```
*      F01CRF Example Program Text
*      Mark 14 Revised. NAG Copyright 1989.
*      .. Parameters ..
      INTEGER          M, N, MN, LMOVE
      PARAMETER        (M=3,N=7,MN=M*N,LMOVE=(M+N)/2)
      INTEGER          NOUT
      PARAMETER        (NOUT=6)
*      .. Local Scalars ..
      INTEGER          I, IFAIL
*      .. Local Arrays ..
      DOUBLE PRECISION A(MN)
      INTEGER          MOVE(LMOVE)
*      .. External Subroutines ..
      EXTERNAL         F01CRF
```

```

*      .. Intrinsic Functions ..
      INTRINSIC          DBLE
*      .. Executable Statements ..
      WRITE (NOUT,*) 'F01CRF Example Program Results'
      DO 20 I = 1, MN
        A(I) = DBLE(I)
20    CONTINUE
      IFAIL = 1

*
      CALL F01CRF(A,M,N,MN,MOVE,LMOVE,IFAIL)

*
      IF (IFAIL.EQ.0) THEN
        WRITE (NOUT,*)
        WRITE (NOUT,99999) (A(I),I=1,MN)
      ELSE
        WRITE (NOUT,99998) IFAIL
      END IF

*
99999 FORMAT (1X,7F7.1)
99998 FORMAT (1X,/1X,' ** F01CRF returned with IFAIL = ',I5)
      END

```

9.2 Program Data

None.

9.3 Program Results

F01CRF Example Program Results

1.0	4.0	7.0	10.0	13.0	16.0	19.0
2.0	5.0	8.0	11.0	14.0	17.0	20.0
3.0	6.0	9.0	12.0	15.0	18.0	21.0
