

NAG Library Routine Document

F11MGF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

F11MGF computes an estimate of the reciprocal of the condition number of a sparse matrix given an *LU* factorization of the matrix computed by F11MEF.

2 Specification

```
SUBROUTINE F11MGF(NORM, N, IL, LVAL, IU, UVAL, ANORM, RCOND, IFAIL)
INTEGER          N, IL(*), IU(*), IFAIL
double precision LVAL(*), UVAL(*), ANORM, RCOND
CHARACTER*1      NORM
```

3 Description

F11MGF estimates the condition number of a real sparse matrix A , in either the 1-norm or the ∞ -norm:

$$\kappa_1(A) = \|A\|_1 \|A^{-1}\|_1 \quad \text{or} \quad \kappa_\infty(A) = \|A\|_\infty \|A^{-1}\|_\infty.$$

Note that $\kappa_\infty(A) = \kappa_1(A^T)$.

Because the condition number is infinite if A is singular, the routine actually returns an estimate of the **reciprocal** of the condition number.

The routine should be preceded by a call to F11MLF to compute $\|A\|_1$ or $\|A\|_\infty$, and a call to F11MEF to compute the *LU* factorization of A . The routine then estimates $\|A^{-1}\|_1$ or $\|A^{-1}\|_\infty$ and computes the reciprocal of the condition number.

4 References

None.

5 Parameters

- 1: NORM – CHARACTER*1 *Input*
On entry: indicates whether $\kappa_1(A)$ or $\kappa_\infty(A)$ is to be estimated.
 NORM = '1' or 'O'
 $\kappa_1(A)$ is estimated.
 NORM = 'I'
 $\kappa_\infty(A)$ is estimated.
Constraint: NORM = '1', 'O' or 'I'.
- 2: N – INTEGER *Input*
On entry: n , the order of the matrix A .
Constraint: $N \geq 0$.

- 3: IL(*) – INTEGER array *Input*
Note: the dimension of the array IL must be at least as large as the dimension of the array of the same name in F11MEF.
On entry: records the sparsity pattern of matrix L as computed by F11MEF.
- 4: LVAL(*) – **double precision** array *Input*
Note: the dimension of the array LVAL must be at least as large as the dimension of the array of the same name in F11MEF.
On entry: records the nonzero values of matrix L and some nonzero values of matrix U as computed by F11MEF.
- 5: IU(*) – INTEGER array *Input*
Note: the dimension of the array IU must be at least as large as the dimension of the array of the same name in F11MEF.
On entry: records the sparsity pattern of matrix U as computed by F11MEF.
- 6: UVAL(*) – **double precision** array *Input*
Note: the dimension of the array UVAL must be at least as large as the dimension of the array of the same name in F11MEF.
On entry: records some nonzero values of matrix U as computed by F11MEF.
- 7: ANORM – **double precision** *Input*
On entry: if NORM = '1' or 'O', the 1-norm of the matrix A .
 If NORM = 'I', the ∞ -norm of the matrix A .
 ANORM may be computed by calling F11MLF with the same value for the parameter NORM.
Constraint: ANORM $\geq$ 0.0.
- 8: RCOND – **double precision** *Output*
On exit: an estimate of the reciprocal of the condition number of A . RCOND is set to zero if exact singularity is detected or the estimate underflows. If RCOND is less than **machine precision**, A is singular to working precision.
- 9: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry $\text{IFAIL} = 0$ or -1 , explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

$\text{IFAIL} = 1$

On entry, $\text{NORM} \neq '1', 'O' \text{ or } 'I'$,
or $N < 0$,
or $\text{ANORM} < 0.0$.

$\text{IFAIL} = 301$

Unable to allocate required internal workspace.

7 Accuracy

The computed estimate RCOND is never less than the true value ρ , and in practice is nearly always less than 10ρ , although examples can be constructed where RCOND is much larger.

8 Further Comments

A call to F11MGF involves solving a number of systems of linear equations of the form $Ax = b$ or $A^T x = b$.

9 Example

This example estimates the condition number in the 1-norm of the matrix A , where

$$A = \begin{pmatrix} 2.00 & 1.00 & 0 & 0 & 0 \\ 0 & 0 & 1.00 & -1.00 & 0 \\ 4.00 & 0 & 1.00 & 0 & 1.00 \\ 0 & 0 & 0 & 1.00 & 2.00 \\ 0 & -2.00 & 0 & 0 & 3.00 \end{pmatrix}.$$

Here A is nonsymmetric and must first be factorized by F11MEF . The true condition number in the 1-norm is 20.25.

9.1 Program Text

```
*      F11MGF Example Program Text
*      Mark 21 Release. NAG Copyright 2004.
*      .. Parameters ..
      INTEGER          NIN, NOUT
      PARAMETER        (NIN=5,NOUT=6)
      INTEGER          LA, NMAX
      PARAMETER        (LA=10000,NMAX=1000)
      DOUBLE PRECISION ONE
      PARAMETER        (ONE=1.D0)
*      .. Local Scalars ..
      DOUBLE PRECISION ANORM, FLOP, RCOND, THRESH
      INTEGER          I, IFAIL, N, NNZ, NNZL, NNZU, NZLMX, NZLUMX,
+                     NZUMX
      CHARACTER        NORM, SPEC
*      .. Local Arrays ..
      DOUBLE PRECISION A(LA), LVAL(8*LA), UVAL(8*LA)
      INTEGER          ICOLZP(NMAX+1), IL(7*NMAX+8*LA+4), IPRM(7*NMAX),
+                     IROWIX(LA), IU(2*NMAX+8*LA+1)
*      .. External Subroutines ..
      EXTERNAL         F11MDF, F11MEF, F11MGF, F11MLF
*      .. Executable Statements ..
      WRITE (NOUT,*) 'F11MGF Example Program Results'
```

```

*      Skip heading in data file
      READ (NIN,*)
*
*      Read order of matrix
*
      READ (NIN,*) N
      IF (N.LE.NMAX) THEN
*
*          Read the matrix A
*
          DO 20 I = 1, N + 1
              READ (NIN,*) ICOLZP(I)
20      CONTINUE
          NNZ = ICOLZP(N+1) - 1
          DO 40 I = 1, NNZ
              READ (NIN,*) A(I), IROWIX(I)
40      CONTINUE
*
*          Calculate COLAMD permutation
*
          SPEC = 'M'
          IFAIL = 1
          CALL F11MDF(SPEC,N,ICOLZP,IROWIX,IPRM,IFAIL)
          IF (IFAIL.EQ.0) THEN
*
*              Factorise
*
              THRESH = ONE
              IFAIL = 0
              NZLMX = 8*NNZ
              NZLUMX = 8*NNZ
              NZUMX = 8*NNZ
              CALL F11MEF(N,IROWIX,A,IPRM,THRESH,NZLMX,NZLUMX,NZUMX,IL,
+                  LVAL,IU,UVAL,NNZL,NNZU,FLOP,IFAIL)
*
*              Calculate norm
*
              NORM = '1'
              IFAIL = 0
              CALL F11MLF(NORM,ANORM,N,ICOLZP,IROWIX,A,IFAIL)
*
*              Calculate condition number
*
              IFAIL = 0
              CALL F11MGF(NORM,N,IL,LVAL,IU,UVAL,ANORM,RCOND,IFAIL)
*
*              Output result
*
              WRITE (NOUT,*)
              WRITE (NOUT,*) 'Norm ,Condition number'
              WRITE (NOUT,'(F7.3,A1,F7.3)') ANORM, ' ', 1/RCOND
          ELSE
              WRITE (NOUT,99999) IFAIL
          END IF
*
      END IF
*
99999 FORMAT (1X,/1X,' ** F11MDF returned with IFAIL = ',I5)
      END

```

9.2 Program Data

F11MGF Example Program Data

```

5  N
1
3
5
7
9
12  ICOLZP(I) I=1,..,N+1

```

```
2.  1
4.  3
1.  1
-2. 5
1.  2
1.  3
-1. 2
1.  4
1.  3
2.  4
3.  5      A(I), IROWIX(I) I=1,NNZ
```

9.3 Program Results

F11MGF Example Program Results

Norm ,Condition number
6.000, 20.250
