

NAG Library Routine Document

G03CCF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

G03CCF computes factor score coefficients from the result of fitting a factor analysis model by maximum likelihood as performed by G03CAF.

2 Specification

```

SUBROUTINE G03CCF(METHOD, ROTATE, NVAR, NFAC, FL, LDFL, PSI, E, R, LDR,
1          FS, LDFS, WK, IFAIL)
    INTEGER          NVAR, NFAC, LDFL, LDR, LDFS, IFAIL
    double precision FL(LDFL,NFAC), PSI(NVAR), E(NVAR), R(LDR,*),
1          FS(LDFS,NFAC), WK(NVAR)
    CHARACTER*1      METHOD, ROTATE

```

3 Description

A factor analysis model aims to account for the covariances among p variables, observed on n individuals, in terms of a smaller number, k , of unobserved variables or factors. The values of the factors for an individual are known as factor scores. G03CAF fits the factor analysis model by maximum likelihood and returns the estimated factor loading matrix, Λ , and the diagonal matrix of variances of the unique components, Ψ . To obtain estimates of the factors, a p by k matrix of factor score coefficients, Φ , is formed. The estimated vector of factor scores, $\hat{f}$, is then given by:

$$\hat{f} = x^T \Phi,$$

where x is the vector of observed variables for an individual.

There are two commonly used methods of obtaining factor score coefficients.

The regression method:

$$\Phi = \Psi^{-1} \Lambda (I + \Lambda^T \Psi^{-1} \Lambda)^{-1},$$

and Bartlett's method:

$$\Phi = \Psi^{-1} \Lambda (\Lambda^T \Psi^{-1} \Lambda)^{-1}.$$

See Lawley and Maxwell (1971) for details of both methods. In the regression method as given above, it is assumed that the factors are not correlated and have unit variance; this is true for models fitted by G03CAF. Further, for models fitted by G03CAF,

$$\Lambda^T \Psi^{-1} \Lambda = \Theta - I,$$

where Θ is the diagonal matrix of eigenvalues of the matrix S^* , as described in G03CAF.

The factors may be orthogonally rotated using an orthogonal rotation matrix, R , as computed by G03BAF. The factor scores for the rotated matrix are then given by ΛR .

4 References

Lawley D N and Maxwell A E (1971) *Factor Analysis as a Statistical Method* (2nd Edition) Butterworths

5 Parameters

- 1: METHOD – CHARACTER*1 *Input*
On entry: indicates which method is to be used to compute the factor score coefficients.
METHOD = 'R'
 The regression method is used.
METHOD = 'B'
 Bartlett's method is used.
Constraint: METHOD = 'B' or 'R'.

- 2: ROTATE – CHARACTER*1 *Input*
On entry: indicates whether a rotation is to be applied.
ROTATE = 'R'
 A rotation will be applied to the coefficients and the rotation matrix, R , must be given in R.
ROTATE = 'U'
 No rotation is applied.
Constraint: ROTATE = 'R' or 'U'.

- 3: NVAR – INTEGER *Input*
On entry: p , the number of observed variables in the factor analysis.
Constraint: $NVAR \geq NFAC$.

- 4: NFAC – INTEGER *Input*
On entry: k , the number of factors in the factor analysis.
Constraint: $NFAC \geq 1$.

- 5: FL(LDFL,NFAC) – **double precision** array *Input*
On entry: A , the matrix of unrotated factor loadings as returned by G03CAF.

- 6: LDFL – INTEGER *Input*
On entry: the first dimension of the array FL as declared in the (sub)program from which G03CCF is called.
Constraint: $LDFL \geq NVAR$.

- 7: PSI(NVAR) – **double precision** array *Input*
On entry: the diagonal elements of Ψ , as returned by G03CAF.
Constraint: $PSI(i) > 0.0$, for $i = 1, 2, \dots, p$.

- 8: E(NVAR) – **double precision** array *Input*
On entry: the eigenvalues of the matrix S^* , as returned by G03CAF.
Constraint: $E(i) > 1.0$, for $i = 1, 2, \dots, p$.

- 9: R(LDR,*) – **double precision** array *Input*
Note: the second dimension of the array R must be at least 1 if ROTATE = 'U' and at least NFAC if ROTATE = 'R'.
On entry: if ROTATE = 'R', R must contain the orthogonal rotation matrix, R , as returned by G03BAF.
 If ROTATE = 'U', R need not be set.
- 10: LDR – INTEGER *Input*
On entry: the first dimension of the array R as declared in the (sub)program from which G03CCF is called.
Constraints:
 if ROTATE = 'R', $LDR \geq NFAC$;
 otherwise 1.
- 11: FS(LDFS,NFAC) – **double precision** array *Output*
On exit: the matrix of factor score coefficients, Φ . $FS(i, j)$ contains the factor score coefficient for the j th factor and the i th observed variable, for $i = 1, 2, \dots, p$ and $j = 1, 2, \dots, k$.
- 12: LDFS – INTEGER *Input*
On entry: the first dimension of the array FS as declared in the (sub)program from which G03CCF is called.
Constraint: $LDFS \geq NVAR$.
- 13: WK(NVAR) – **double precision** array *Workspace*
- 14: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, NFAC < 1,
 or NVAR < NFAC,
 or LDFL < NVAR,
 or LDFS < NVAR,
 or ROTATE = 'R' and LDR < NFAC,
 or METHOD $\neq$ 'R' or 'B',
 or ROTATE $\neq$ 'R' or 'U'.

IFAIL = 2

On entry, a value of $\text{PSI} \leq 0.0$,
or a value of $E \leq 1.0$.

7 Accuracy

Accuracy will depend on the accuracy requested when computing the estimated factor loadings using G03CAF.

8 Further Comments

To compute the factor scores using the factor score coefficients the values for the observed variables first need to be standardized by subtracting the sample means and, if the factor analysis is based upon a correlation matrix, dividing by the sample standard deviations. This may be performed using G03ZAF. The standardized variables are then post-multiplied by the factor score coefficients. This may be performed using routines from Chapter F06, for example F06YAF (DGEMM).

If principal component analysis is required the routine G03AAF computes the principal component scores directly. Hence, the factor score coefficients are not needed.

9 Example

This example is taken from Lawley and Maxwell (1971). The correlation matrix for 220 observations on six school subjects is input and a factor analysis model with two factors fitted using G03CAF. The factor score coefficients are computed using the regression method.

9.1 Program Text

```
*      G03CCF Example Program Text
*      Mark 15 Release. NAG Copyright 1991.
*      .. Parameters ..
      INTEGER          NIN, NOUT
      PARAMETER        (NIN=5,NOUT=6)
      INTEGER          NMAX, MMAX, LWK, LDX, LDFL, LDR, LDFS
      PARAMETER        (NMAX=20,MMAX=10,LWK=400,LDX=NMAX,LDFL=MMAX,
+                      LDR=MMAX,LDFS=MMAX)
*      .. Local Scalars ..
      INTEGER          I, IFAIL, J, M, N, NFAC, NVAR
      CHARACTER        MATRIX, METHOD, WEIGHT
*      .. Local Arrays ..
      DOUBLE PRECISION COM(MMAX), E(MMAX), FL(LDFL,MMAX), FS(LDFS,MMAX),
+                      PSI(MMAX), R(LDR,MMAX), STAT(4), WK(LWK),
+                      WT(NMAX), X(LDX,MMAX)
      INTEGER          IOP(5), ISX(MMAX), IWK(4*MMAX+2)
*      .. External Subroutines ..
      EXTERNAL         G03CAF, G03CCF
*      .. Executable Statements ..
      WRITE (NOUT,*) 'G03CCF Example Program Results'
*      Skip headings in data file
      READ (NIN,*)
      READ (NIN,*) MATRIX, WEIGHT, N, M, NVAR, NFAC
      IF (M.LE.MMAX .AND. (MATRIX.EQ.'C' .OR. MATRIX.EQ.'c' .OR. N.LE.
+                      NMAX)) THEN
          IF (MATRIX.EQ.'C' .OR. MATRIX.EQ.'c') THEN
              DO 20 I = 1, M
                  READ (NIN,*) (X(I,J),J=1,M)
20             CONTINUE
          ELSE
              IF (WEIGHT.EQ.'W' .OR. WEIGHT.EQ.'w') THEN
                  DO 40 I = 1, N
                      READ (NIN,*) (X(I,J),J=1,M), WT(I)
40             CONTINUE
              ELSE
                  DO 60 I = 1, N
```

```

        READ (NIN,*) (X(I,J),J=1,M)
60      CONTINUE
        END IF
        END IF
        READ (NIN,*) (ISX(J),J=1,M)
        READ (NIN,*) (IOP(J),J=1,5)
        IFAIL = 1
*
        CALL G03CAF(MATRIX,WEIGHT,N,M,X,LDX,NVAR,ISX,NFAC,WT,E,STAT,
+              COM,PSI,R,FL,LDFL,IOP,IWK,WK,LWK,IFAIL)
*
        IF (IFAIL.EQ.0 .OR. IFAIL.GT.4) THEN
            WRITE (NOUT,*)
            WRITE (NOUT,*) ' Loadings, Communalities and PSI'
            WRITE (NOUT,*)
            DO 80 I = 1, NVAR
                WRITE (NOUT,99999) (FL(I,J),J=1,NFAC), COM(I), PSI(I)
80          CONTINUE
            READ (NIN,*) METHOD
            IFAIL = 1
*
            CALL G03CCF(METHOD,'U',NVAR,NFAC,FL,LDFL,PSI,E,R,LDR,FS,
+              LDFS,WK,IFAIL)
*
            IF (IFAIL.EQ.0) THEN
                WRITE (NOUT,*)
                WRITE (NOUT,*) ' Factor score coefficients'
                WRITE (NOUT,*)
                DO 100 I = 1, NVAR
                    WRITE (NOUT,99999) (FS(I,J),J=1,NFAC)
100          CONTINUE
            ELSE
                WRITE (NOUT,*)
                WRITE (NOUT,99998) ' ** G03CCF returned with IFAIL = ',
+              IFAIL
            END IF
*
            ELSE
                WRITE (NOUT,99998) ' ** G03CAF returned with IFAIL = ',
+              IFAIL
            END IF
        END IF
*
99999 FORMAT (2X,4F8.3)
99998 FORMAT (1X,A,I5)
END

```

9.2 Program Data

G03CCF Example Program Data

```

'C' 'U' 220 6 6 2
1.000 0.439 0.410 0.288 0.329 0.248
0.439 1.000 0.351 0.354 0.320 0.329
0.410 0.351 1.000 0.164 0.190 0.181
0.288 0.354 0.164 1.000 0.595 0.470
0.329 0.320 0.190 0.595 1.000 0.464
0.248 0.329 0.181 0.470 0.464 1.000
  1   1   1   1   1   1
1 -1 500 3 5
'R'

```

9.3 Program Results

G03CCF Example Program Results

Loadings, Communalities and PSI

0.553	-0.429	0.490	0.510
0.568	-0.288	0.406	0.594
0.392	-0.450	0.356	0.644

0.740	0.273	0.623	0.377
0.724	0.211	0.569	0.431
0.595	0.132	0.372	0.628

Factor score coefficients

0.193	-0.392
0.170	-0.226
0.109	-0.326
0.349	0.337
0.299	0.229
0.169	0.098
