

NAG Library Routine Document

F06PAF (DGEMV)

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

F06PAF (DGEMV) performs one of the matrix-vector operations

$$y \leftarrow \alpha Ax + \beta y, \quad \text{or} \quad y \leftarrow \alpha A^T x + \beta y,$$

where A is an m by n real matrix, x and y are real vectors, and α and β are real scalars.

If $m = 0$ or $n = 0$, no operation is performed.

2 Specification

```
SUBROUTINE F06PAF(TRANS, M, N, ALPHA, A, LDA, X, INCX, BETA, Y, INCY)
  INTEGER          M, N, LDA, INCX, INCY
  double precision ALPHA, A(LDA,*), X(*), BETA, Y(*)
  CHARACTER*1      TRANS
```

The routine may be called by its BLAS name ***dgemv***.

3 Description

None.

4 References

None.

5 Parameters

- | | | |
|----|---|--------------|
| 1: | TRANS – CHARACTER*1
<i>On entry:</i> specifies the operation to be performed.
TRANS = 'N'
$y \leftarrow \alpha Ax + \beta y.$
TRANS = 'T' or 'C'
$y \leftarrow \alpha A^T x + \beta y.$
<i>Constraint:</i> TRANS = 'N', 'T' or 'C'. | <i>Input</i> |
| 2: | M – INTEGER
<i>On entry:</i> m , the number of rows of the matrix A .
<i>Constraint:</i> $M \geq 0$. | <i>Input</i> |
| 3: | N – INTEGER
<i>On entry:</i> n , the number of columns of the matrix A .
<i>Constraint:</i> $N \geq 0$. | <i>Input</i> |

- 4: ALPHA – *double precision* *Input*
On entry: the scalar α .
- 5: A(LDA,*) – *double precision* array *Input*
Note: the second dimension of the array A must be at least N.
On entry: the m by n matrix A .
- 6: LDA – INTEGER *Input*
On entry: the first dimension of the array A as declared in the (sub)program from which F06PAF (DGEMV) is called.
Constraint: $LDA \geq \max(1, M)$.
- 7: X(*) – *double precision* array *Input*
Note: the dimension of the array X must be at least $1 + (N - 1)|INCX|$ if TRANS = 'N' and at least $1 + (M - 1)|INCX|$ if TRANS = 'T' or 'C'.
On entry: the incremented array X must contain the vector x .
- 8: INCX – INTEGER *Input*
On entry: the increment in the subscripts of X between successive elements of x .
Constraint: $INCX \neq 0$.
- 9: BETA – *double precision* *Input*
On entry: the scalar β .
- 10: Y(*) – *double precision* array *Input/Output*
Note: the dimension of the array Y must be at least $1 + (M - 1)|INCY|$ if TRANS = 'N' and at least $1 + (N - 1)|INCY|$ if TRANS = 'T' or 'C'.
On entry: the incremented array Y must contain the vector y .
On exit: the updated vector y .
- 11: INCY – INTEGER *Input*
On entry: the increment in the subscripts of Y between successive elements of y .
Constraint: $INCY \neq 0$.

6 Error Indicators and Warnings

None.

7 Accuracy

Not applicable.

8 Further Comments

None.

9 Example

None.