

NAG Library Routine Document

F08QLF (DTRSNA)

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

F08QLF (DTRSNA) estimates condition numbers for specified eigenvalues and/or right eigenvectors of a real upper quasi-triangular matrix.

2 Specification

```

SUBROUTINE F08QLF(JOB, HOWMNY, SELECT, N, T, LDT, VL, LDVL, VR, LDVR, S,
1 SEP, MM, M, WORK, LDWORK, IWORK, INFO)
    INTEGER          N, LDT, LDVL, LDVR, MM, M, LDWORK, IWORK(*), INFO
    double precision T(LDT,*), VL(LDVL,*), VR(LDVR,*), S(*), SEP(*),
1 WORK(LDWORK,*)
    LOGICAL          SELECT(*)
    CHARACTER*1      JOB, HOWMNY

```

The routine may be called by its LAPACK name ***dtrsna***.

3 Description

F08QLF (DTRSNA) estimates condition numbers for specified eigenvalues and/or right eigenvectors of a real upper quasi-triangular matrix T in canonical Schur form. These are the same as the condition numbers of the eigenvalues and right eigenvectors of an original matrix $A = ZZ^T$ (with orthogonal Z), from which T may have been derived.

F08QLF (DTRSNA) computes the reciprocal of the condition number of an eigenvalue λ_i as

$$s_i = \frac{|v^H u|}{\|u\|_E \|v\|_E},$$

where u and v are the right and left eigenvectors of T , respectively, corresponding to λ_i . This reciprocal condition number always lies between zero (i.e., ill-conditioned) and one (i.e., well-conditioned).

An approximate error estimate for a computed eigenvalue λ_i is then given by

$$\frac{\epsilon \|T\|}{s_i},$$

where ϵ is the ***machine precision***.

To estimate the reciprocal of the condition number of the right eigenvector corresponding to λ_i , the routine first calls F08QFF (DTREXC) to reorder the eigenvalues so that λ_i is in the leading position:

$$T = Q \begin{pmatrix} \lambda_i & c^T \\ 0 & T_{22} \end{pmatrix} Q^T.$$

The reciprocal condition number of the eigenvector is then estimated as sep_i , the smallest singular value of the matrix $(T_{22} - \lambda_i I)$. This number ranges from zero (i.e., ill-conditioned) to very large (i.e., well-conditioned).

An approximate error estimate for a computed right eigenvector u corresponding to λ_i is then given by

$$\frac{\epsilon \|T\|}{sep_i}.$$

4 References

Golub G H and Van Loan C F (1996) *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

5 Parameters

- 1: JOB – CHARACTER*1 *Input*
On entry: indicates whether condition numbers are required for eigenvalues and/or eigenvectors.
 JOB = 'E'
 Condition numbers for eigenvalues only are computed.
 JOB = 'V'
 Condition numbers for eigenvectors only are computed.
 JOB = 'B'
 Condition numbers for both eigenvalues and eigenvectors are computed.
Constraint: JOB = 'E', 'V' or 'B'.
- 2: HOWMNY – CHARACTER*1 *Input*
On entry: indicates how many condition numbers are to be computed.
 HOWMNY = 'A'
 Condition numbers for all eigenpairs are computed.
 HOWMNY = 'S'
 Condition numbers for selected eigenpairs (as specified by SELECT) are computed.
Constraint: HOWMNY = 'A' or 'S'.
- 3: SELECT(*) – LOGICAL array *Input*
Note: the dimension of the array SELECT must be at least $\max(1, N)$ if HOWMNY = 'S', and at least 1 otherwise.
On entry: specifies the eigenpairs for which condition numbers are to be computed if HOWMNY = 'S'. To select condition numbers for the eigenpair corresponding to the real eigenvalue λ_j , SELECT(*j*) must be set .TRUE.. To select condition numbers corresponding to a complex conjugate pair of eigenvalues λ_j and λ_{j+1} , SELECT(*j*) and/or SELECT(*j* + 1) must be set to .TRUE..
 If HOWMNY = 'A', SELECT is not referenced.
- 4: N – INTEGER *Input*
On entry: *n*, the order of the matrix *T*.
Constraint: $N \geq 0$.
- 5: T(LDT,*) – **double precision** array *Input*
Note: the second dimension of the array T must be at least $\max(1, N)$.
On entry: the *n* by *n* upper quasi-triangular matrix *T* in canonical Schur form, as returned by F08PEF (DHSEQR).
- 6: LDT – INTEGER *Input*
On entry: the first dimension of the array T as declared in the (sub)program from which F08QLF (DTRSNA) is called.
Constraint: $LDT \geq \max(1, N)$.

- 7: VL(LDVL,*) – **double precision** array *Input*
Note: the second dimension of the array VL must be at least $\max(1, MM)$ if JOB = 'E' or 'B' and at least 1 if JOB = 'V'.
On entry: if JOB = 'E' or 'B', VL must contain the left eigenvectors of T (or of any matrix QTQ^T with Q orthogonal) corresponding to the eigenpairs specified by HOWMNY and SELECT. The eigenvectors **must** be stored in consecutive columns of VL, as returned by F08PKF (DHSEIN) or F08QKF (DTREVC).
 If JOB = 'V', VL is not referenced.
- 8: LDVL – INTEGER *Input*
On entry: the first dimension of the array VL as declared in the (sub)program from which F08QLF (DTRSNA) is called.
Constraints:
 if JOB = 'E' or 'B', $LDVL \geq \max(1, N)$;
 if JOB = 'V', $LDVL \geq 1$.
- 9: VR(LDVR,*) – **double precision** array *Input*
Note: the second dimension of the array VR must be at least $\max(1, MM)$ if JOB = 'E' or 'B' and at least 1 if JOB = 'V'.
On entry: if JOB = 'E' or 'B', VR must contain the right eigenvectors of T (or of any matrix QTQ^T with Q orthogonal) corresponding to the eigenpairs specified by HOWMNY and SELECT. The eigenvectors **must** be stored in consecutive columns of VR, as returned by F08PKF (DHSEIN) or F08QKF (DTREVC).
 If JOB = 'V', VR is not referenced.
- 10: LDVR – INTEGER *Input*
On entry: the first dimension of the array VR as declared in the (sub)program from which F08QLF (DTRSNA) is called.
Constraints:
 if JOB = 'E' or 'B', $LDVR \geq \max(1, N)$;
 if JOB = 'V', $LDVR \geq 1$.
- 11: S(*) – **double precision** array *Output*
Note: the dimension of the array S must be at least $\max(1, MM)$ if JOB = 'E' or 'B' and at least 1 if JOB = 'V'.
On exit: the reciprocal condition numbers of the selected eigenvalues if JOB = 'E' or 'B', stored in consecutive elements of the array. Thus $S(j)$, $SEP(j)$ and the j th columns of VL and VR all correspond to the same eigenpair (but not in general the j th eigenpair unless all eigenpairs have been selected). For a complex conjugate pair of eigenvalues, two consecutive elements of S are set to the same value.
 S is not referenced if JOB = 'V'.
- 12: SEP(*) – **double precision** array *Output*
Note: the dimension of the array SEP must be at least $\max(1, MM)$ if JOB = 'V' or 'B' and at least 1 if JOB = 'E'.
On exit: the estimated reciprocal condition numbers of the selected right eigenvectors if JOB = 'V' or 'B', stored in consecutive elements of the array. For a complex eigenvector, two consecutive elements of SEP are set to the same value. If the eigenvalues cannot be reordered to compute $SEP(j)$, then $SEP(j)$ is set to zero; this can only occur when the true value would be very small anyway.

If JOB = 'E', SEP is not referenced.

- 13: MM – INTEGER *Input*
On entry: the number of elements in the arrays S and SEP, and the number of columns in the arrays VL and VR (if used). The precise number required, m , is n if HOWMNY = 'A'; if HOWMNY = 'S', m is obtained by counting 1 for each selected real eigenvalue, and 2 for each selected complex conjugate pair of eigenvalues (see SELECT), in which case $0 \leq m \leq n$.
Constraint: $MM \geq M$.
- 14: M – INTEGER *Output*
On exit: m , the number of elements of S and/or SEP actually used to store the estimated condition numbers. If HOWMNY = 'A', M is set to n .
- 15: WORK(LDWORK,*) – **double precision** array *Workspace*
Note: the second dimension of the array WORK must be at least $\max(1, N + 6)$ if JOB = 'V' or 'B' and at least 1 if JOB = 'E'.
 If JOB = 'E', WORK is not referenced.
- 16: LDWORK – INTEGER *Input*
On entry: the first dimension of the array WORK as declared in the (sub)program from which F08QLF (DTRSNA) is called.
Constraints:
 if JOB = 'V' or 'B', $LDWORK \geq \max(1, N)$;
 if JOB = 'E', $LDWORK \geq 1$.
- 17: IWORK(*) – INTEGER array *Workspace*
Note: the dimension of the array IWORK must be at least $\max(1, 2 \times (N - 1))$.
- 18: INFO – INTEGER *Output*
On exit: INFO = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

INFO < 0

If $INFO = -i$, argument i had an illegal value. An explanatory message is output, and execution of the program is terminated.

7 Accuracy

The computed values sep_i may over estimate the true value, but seldom by a factor of more than 3.

8 Further Comments

For a description of canonical Schur form, see the document for F08PEF (DHSEQR).

The complex analogue of this routine is F08QYF (ZTRSNA).

9 Example

This example computes approximate error estimates for all the eigenvalues and right eigenvectors of the matrix T , where

$$T = \begin{pmatrix} 0.7995 & -0.1144 & 0.0060 & 0.0336 \\ 0.0000 & -0.0994 & 0.2478 & 0.3474 \\ 0.0000 & -0.6483 & -0.0994 & 0.2026 \\ 0.0000 & 0.0000 & 0.0000 & -0.1007 \end{pmatrix}.$$

9.1 Program Text

```
*      F08QLF Example Program Text
*      Mark 21 Release. NAG Copyright 2004.
*      .. Parameters ..
      INTEGER          NIN, NOUT
      PARAMETER        (NIN=5,NOUT=6)
      INTEGER          NMAX
      PARAMETER        (NMAX=8)
      INTEGER          LDT, LDVL, LDVR, LDWORK
      PARAMETER        (LDT=NMAX,LDVL=NMAX,LDVR=NMAX,LDWORK=NMAX)
*      .. Local Scalars ..
      DOUBLE PRECISION EPS, TNORM
      INTEGER          I, INFO, J, M, N
*      .. Local Arrays ..
      DOUBLE PRECISION S(NMAX), SEP(NMAX), T(LDT,NMAX), VL(LDVL,NMAX),
+      VR(LDVR,NMAX), WORK(LDWORK,NMAX+6)
      INTEGER          IWORK(2*NMAX-1)
      LOGICAL          SELECT(1)
*      .. External Functions ..
      DOUBLE PRECISION F06RAF, X02AJF
      EXTERNAL          F06RAF, X02AJF
*      .. External Subroutines ..
      EXTERNAL          DTREVC, DTRSNA
*      .. Executable Statements ..
      WRITE (NOUT,*) 'F08QLF Example Program Results'
      WRITE (NOUT,*)
*      Skip heading in data file
      READ (NIN,*)
      READ (NIN,*) N
      IF (N.LE.NMAX) THEN
*
*         Read T from data file
*
*         READ (NIN,*) ((T(I,J),J=1,N),I=1,N)
*
*         Calculate the left and right eigenvectors of T
*
*         CALL DTREVC('Both','All',SELECT,N,T,LDT,VL,LDVL,VR,LDVR,N,M,
+         WORK,INFO)
*
*         Estimate condition numbers for all the eigenvalues and right
*         eigenvectors of T
*
*         CALL DTRSNA('Both','All',SELECT,N,T,LDT,VL,LDVL,VR,LDVR,S,SEP,
+         N,M,WORK,LDWORK,IWORK,INFO)
*
*         Print condition numbers of eigenvalues and right eigenvectors
*
*         WRITE (NOUT,*) 'S'
*         WRITE (NOUT,99999) (S(I),I=1,M)
*         WRITE (NOUT,*)
*         WRITE (NOUT,*) 'SEP'
*         WRITE (NOUT,99999) (SEP(I),I=1,M)
*
*         Calculate approximate error estimates (using the 1-norm)
*
*         EPS = X02AJF()
*         TNORM = F06RAF('1-norm',N,N,T,LDT,WORK)
*         WRITE (NOUT,*)
```

```

      WRITE (NOUT,*) 'Approximate error estimates for eigenvalues ',
+      'of T (machine-dependent)'
      WRITE (NOUT,99999) (EPS*TNORM/S(I),I=1,M)
      WRITE (NOUT,*)
      WRITE (NOUT,*) 'Approximate error estimates for right ',
+      'eigenvectors of T (machine-dependent)'
      WRITE (NOUT,99999) (EPS*TNORM/SEP(I),I=1,M)
      ELSE
        WRITE (NOUT,*) 'NMAX too small'
      END IF
*
99999 FORMAT ((3X,1P,7E11.1))
      END

```

9.2 Program Data

F08QLF Example Program Data

4				:Value of N
0.7995	-0.1144	0.0060	0.0336	
0.0000	-0.0994	0.2478	0.3474	
0.0000	-0.6483	-0.0994	0.2026	
0.0000	0.0000	0.0000	-0.1007	:End of matrix T

9.3 Program Results

F08QLF Example Program Results

S	9.9E-01	7.0E-01	7.0E-01	5.7E-01
---	---------	---------	---------	---------

SEP	6.3E-01	3.7E-01	3.7E-01	3.1E-01
-----	---------	---------	---------	---------

Approximate error estimates for eigenvalues of T (machine-dependent)	9.6E-17	1.4E-16	1.4E-16	1.7E-16
--	---------	---------	---------	---------

Approximate error estimates for right eigenvectors of T (machine-dependent)	1.5E-16	2.6E-16	2.6E-16	3.1E-16
---	---------	---------	---------	---------
